
Protocol Principles

Layering, CL versus CO Service, ARQ Techniques, Sequence Numbers, Windowing, Flow Control

Agenda
Introduction
 <u>3 Layer Model and Service Types</u>
 ARQ Techniques
– Introduction
– Idle RQ
 Continuous RQ
Selective Acknowledgement
GoBackN
 Positive Acknowledgement
Selective Reject
 Sequence Numbers and Windowing
 Delay Bandwidth Product
– Flow Control
– HDLC Overview
© 2008, D.I. Manfred Lindner Protocol Principles, v4.8 2




Two Important Principles for Data Communication


Layering


- Structuring the complex task of data communication into smaller pieces by usage of "layers"
- A layer is built by the resources of the corresponding protocol peer entities and by the protocol procedures performed between them
 - protocol standards define fields of the control field of a frame (bits seen on the wire) and the communication behavior of the peers receiving and sending frames
- A layer is using the services of the lower layers to provide a enhanced service to the upper layer
 - The application layer can access the lower layer (the protocol stack) via API (application programming interface)
 - The communication layer can access the lower layer via network-card driver
- Connectionless versus connection-oriented service


© 2008, D.I. Manfred Lindner


Protocol Principles, v4.8






















Agenda			
Introduction			
 – 3 Layer Model and Service Types 			
ARQ Technie	ques		
 Introduction 			
– Idle RQ			
– Continuous RQ			
Selective A	cknowledgement		
 GoBackN 			
	knowledgement		
 Selective R 	eject		
 Sequence Numbers and Windowing 			
 Delay Bandwidth Product 			
 Flow Control 	l		
- HDLC Overv	view		
© 2008, D.I. Manfred Lindner	Protocol Principles, v4.8	12	




























Idle-RQ	
 simple ARQ implementation 	
 stop & wait protocol 	
 device waits for the acknowledgement (ACK) before sending the next data frame 	
 basic method can be improved by NACK 	
 two identifiers are necessary (0, 1) 	
 distinction between new data frame or duplicate frame 	
 numbering of data frames 	
– modulo 2	
 half duplex protocol 	
 full duplex lines can not be efficiently used 	
© 2008, D.I. Manfred Lindner Protocol Principles, v4.8 22	




























Agenda
Introduction
 – 3 Layer Model and Service Types
ARQ Techniques
– Introduction
– Idle RQ
– <u>Continuous RQ</u>
 <u>Selective Acknowledgement</u>
 GoBackN
 Positive Acknowledgement
 Selective Reject
 Sequence Numbers and Windowing
 Delay Bandwidth Product
– Flow Control
– HDLC Overview
© 2008, D.I. Manfred Lindner Protocol Principles, v4.8 32
















GoBackN	
• principle	
	ors, all data frames since "N" will be ain by NACK(N) (Negative Ack.)
	rames are discarded by receiver until frame sequence number arrives
	s not necessary in this case ver could be kept more simple
Ŭ	nowledgments could confirm multiple data iple acknowledgement)
 often use to 	spare number of Ack's in opposite direction
 – each transmi 	tted data frame starts an individual timer
• which will be	e reset, if acknowledgement is received
 if timeout or 	ccurs data frame is sent once again (scenario 3)
© 2008, D.I. Manfred Lindner	Protocol Principles, v4.8 38







































Agenda			
Introduction	1		
 – 3 Layer Model and Service Types 			
• ARQ Techni	iques		
 Introduction 			
– Idle RQ			
– Continuous RQ			
 Selective A 	Acknowledgement		
 GoBackN 			
 Positive Ac 	cknowledgement		
 Selective F 	Reject		
– <u>Sequence</u> N	Jumbers and Windowing		
 Delay Band 	width Product		
 Flow Control 	bl		
– HDLC Over	view		
© 2008, D.I. Manfred Lindner	Protocol Principles, v4.8	52	













© 2008, D.I. Manfred Lindner


Page 02 - 28











































Agenda
Introduction
 – 3 Layer Model and Service Types
ARQ Techniques
– Introduction
– Idle RQ
– Continuous RQ
 Selective Acknowledgement
GoBackN
Positive Acknowledgement
Selective Reject
 Sequence Numbers and Windowing
 Delay Bandwidth Product
– Flow Control
– HDLC Overview
© 2008, D.I. Manfred Lindner Protocol Principles, v4.8 72


				~ 9'	VCII	INUI	Innei	r of E	Jyle	5
S or	rializa	tion Dolou	(in mc)	[(Numb	or of Dud	······································	/ (Ditrot	o in coo)	1 * 1000	
<u>Ser</u>	rializa	tion Delay	<u>(</u> (m ms) =	מחוועו) ן	er or Byr	.es 8)	/ (Billai	e in sec)] 1000	
В	Bitrate	9,6 kbit/s	48 kbit/s	128 kbit/s	2,048 Mbit/s	10 Mbit/s	100 Mbit/s	155 Mbit/s	622 Mbit/s	1 Gigabit/s
	umber f Byte	Delay in msec (10 ⁻³)	Delay in msec (10 ⁻³)	Delay in msec (10 ⁻³)	Delay in msec (10 ⁻³)	Delay in msec (10 ⁻³)	Delay in msec (10 ⁻³)	Delay in msec (10 ⁻³)	Delay in msec (10 ⁻³)	Delay in msec (10 ⁻³
Bit 0	0,125	0,104167	0,020833	0,007813	0.000488	0,000100	0,000010	0,00006	0,00002	0,00000
Byte	1	0,833333	0,166667	0,062500				0.000052	0.000013	0.00000
PCM-30	32	26,666667	5,333333	2,000000	-,		0,002560	0.001652	0.000412	0,00025
ATM cell	53	44,166667	8,833333	3,312500		0,042400		0,002735	0,000682	0,00042
Ethernet	64	53,333333	10,666667	4,000000	0,250000	0,051200	0,005120	0,003303	0,000823	0,00051
X.25	256	213,333333	42,666667	16,000000	1,000000	0,204800	0,020480	0,013213	0,003293	0,00204
IP	576	480,000000	96,000000	36,000000	2,250000	0,460800	0,046080	0,029729	0,007408	0,00460
Ethernet 1	1.518	1.265,000000	253,000000	94,875000	5,929688	1,214400	0,121440	0,078348	0,019524	0,01214
FR 8	8.192	6.826,666667	1.365,333333	512,000000	32,000000	6,553600	0,655360	0,422813	0,105363	0,06553
TCP 6	5.534	54.611,666667	10.922,333333	4.095,875000	255,992188	52,427200	5,242720	3,382400	0,842881	0,52427
	1	1kbit/s = 1 IKByte = 1(


Propagation (Sig	nal) Del	ау	
Tp = <u>Propagation Delay</u> (in m	s) = [(Distanc	e in m) / (velocity	in m/sec)]* 1000
		v=200.000km/s	v=300.000km/s
	Distance	Delay in msec (10 ⁻³)	Delay in msec (10 ⁻³)
CPU Bus	10 cm	0,0000005	0,0000003
	1 m	0,0000050	0,000033
RS232, V24/V.28	15 m	0,0000750	0,0000500
LAN, Copper, RJ45	100 m	0,0005000	0,0003333
LAN, FO, X.21/V.11-V.10 Local Subscriber Line	1 km	0,0050000	0,0033333
WAN Link Repeater	2,5 km 10 km	0,0125000	0,0083333 0,0333333
WAN Link Repeater	100 km	0,500000	0,3333333
WAN FO Link Repeater	1.000 km	5,000000	3,3333333
WAN FO Link Repeater	10.000 km	50.0000000	33,33333333
Satellite Link	40.000 km	200.0000000	133,33333333
Satellite Link	50.000 km	250,0000000	166,66666667
	100.000 km	500,0000000	333,3333333
	300.000 km	1500,0000000	1000,0000000


ong is a Bit	?		
<u>Length</u> (in m) = [(1	/ (bitrate per	r sec)] * [(velocit	y in m/sec)]
	Bitrate	Bit Length in meter	Bit Length in meter
Analogue Modem	9,6 kbit/s	20833,33	31250,00
Analogue Modem	48 kbit/s	4166,67	6250,00
DS0	64 kbit/s	3125,00	4687,50
ISDN (2B)	128 kbit/s	1562,50	2343,75
PCM-30, E1	2,048 Mbit/s	97,66	146,48
Token Ring 4	4 Mbit/s	50,00	75,00
Ethernet	10 Mbit/s	20,00	30,00
Token Ring16	16 Mbit/s	12,50	18,75
Fast Ethernet, FDDI	100 Mbit/s	2,00	3,00
ATM STM1, OC-3	155 Mbit/s	1,29	1,94
ATM STM4, OC-12	622 Mbit/s	0,32	0,48
Gigabit Ethernet	1 Gigabit/s	0,20	0,30
OC-48	2,5 Gigabit/s	0,08	0,12
10 Gigabit Ethernet	10 Gigabit/s	0,02	0,03
	-	Copper	LWL - Free Space
		200.000 km /sec	300.000 km / sec
















































HDLC	
 <u>High-level Data Link Control</u> most widely used data link control protocol based on building elements synchronous transmission bit-oriented line protocol using bitstuffing Continuous RQ with GoBackN, piggybacked ACK 	
 P/F procedure (see appendix chapter for details) provides many options 	
 half-duplex and full-duplex transmission (see appendix chapter for details) 	
 point-to-point and multipoint configuration (see appendix chapter for details) switched or non-switched channels 	
© 2008, D.I. Manfred Lindner Protocol Principles, v4.8	92












Frame-Types					
Connection-Oriented		Connection-Less			
1	Information		UI	Unnumbered Information	
RR REJ RNR SREJ	Receiver Ready Reject Receiver Not Ready Selective Reject				
SARM SNRME	Set Normal Response Mode Set Async Balanced Mode Set Async Response Mode Set NRM Extended Mode Set ABM Extended Mode			Miscellaneous	
SARME	Set ARM Extended Mode		XID	Exchange Identification	
DISC	Disconnect		UP	Unnumbered Poll	
UA	Unnumbered Acknowledge		SIM RIM	Set Initialization Mode Request Initialization Mode	
RSET FRMR	Reset Frame Reject		NR0-3	Non-Reserved 0	
RD DM	Request Disconnect Disconnect Mode				
2008, D.I. Manf	red Lindner Pr	otocol Principl	es, v4.8		







© 2008, D.I. Manfred Lindner

Page 02 - 50

